

Fundamentals of Data Acquisition Using NI-DAQmx



ni.com

1

Topics

- Data Acquisition Systems
- Sampling and Timing
- The NI-DAQmx Driver
- The NI-DAQmx Application Programming Interface
- Reading or Writing a Finite Amount of Data
- Communicating Data Continuously



4

Data Acquisition Systems



ni.com

5


What is Data Acquisition?

Data Acquisition (DAQ) is the process of sampling signals that represent real world phenomena and converting the samples into digital data that can be manipulated by a computer.




6

Architecture of an Integrated Measurement System



7

What is a Sensor?



Sensors are devices that convert physical phenomena into measurable electrical signals

8

Common Sensors and Transducers


Sensors and Transducers	Phenomenon
Thermocouple, RTD, thermistor	Temperature
Photo sensor	Light
Microphone	Sound
Strain gage, piezoelectric transducer	Force and Pressure
Potentiometer, LVDT, optical encoder	Position and Displacement
Accelerometer	Acceleration
pH probe	pH



9

Types of Signals

Two Types of Electrical Signals




10

Signal Characteristics

What characteristics of a signal can we measure?


Analog

Level is the *steady-state* magnitude of a signal at a particular point in time



Digital

State is the level of a *static* digital signal at a particular point in time, usually shown as “0” or “1”




11

Signal Characteristics

What characteristics of a signal can we measure?


Analog

Shape is the *profile* of a waveform over a period of time



Digital

Pattern is a particular *sequence* of digital states over a period of time




12

Signal Characteristics

What characteristics of a signal can we measure?

Analog

Frequency is the number of times a recurring (*periodic*) waveform occurs in a second




Frequency = 5 Hz



Digital

Rate can be either the number of pulses per second, or the number of bits conveyed each second



Rate = 9 bits/s


13

Signal Characteristics

What characteristics of a signal can we measure?

Analog

Frequency is the number of times a recurring (*periodic*) waveform occurs in a second




Frequency = 5 Hz



Digital


Rate can be either the number of pulses per second, or the number of bits conveyed each second



Rate = 4 pulses/s


14

Signal Conditioning



15


Signal Conditioning Makes Signals Easier to Measure




16

Signal Conditioning for Voltage Measurements


- Amplification




- Filtering



- Attenuation




- Isolation



17

Amplification


- Maximize ADC range
- Increase signal-to-noise ratio (SNR)



18

Attenuation


Brings signal into DAQ device range.



19

Filtering


Removes noise and unwanted frequencies



20

Isolation


Disconnects the signal from the internal DAQ circuitry.



21

Measurement Device

NI Data Acquisition Hardware Families



22

Sampling and Timing



ni.com

23

Analog Input Measurements


Considerations

- How many channels?
- How fast do I need to acquire the signal?
- What's the smallest change in the signal I need to detect?
- What are the expected minimum and maximum values?
- How accurate a measurement do I need?



24

How Fast do I Need to Acquire the Signal?



Sample rate is the frequency at which the ADC converts the signal to samples.



25


The Nyquist Theorem

- You must sample at greater than 2 times the maximum frequency component of your signal to accurately represent the **frequency** of your signal.
- You must sample between 5–10 times greater than the maximum frequency component of your signal to accurately represent the **shape** of your signal.



26

The Nyquist Theorem and Sample Rate




27


Timing

Two types of timing can be used to control when data samples are acquired (or generated):

Software timing: the application software controls when data is acquired or generated



Hardware timing: a digital signal controls when data is acquired or generated



28

Acquisition Modes

On Demand: The device produces a requested sample when prompted by a software acquisition request.

Finite Samples: The DAQ device acquires samples at a specified rate until it reaches the number of total requested samples, and then stops acquiring and sends the data to the computer.

Continuous Samples: The DAQ device acquires samples at a specified rate and sends blocks of samples to the computer when requested, until it receives a command to stop acquiring or encounters an error condition.

Hardware-Timed Single Point (HWTSP): The computer acquires data points one at a time from the DAQ device while the device runs off of a sample clock.


Hardware-Timed




29

Clocks & Triggers

Triggers are digital signals that can be used to cause NI-DAQmx to perform an action



Clocks are a specific type of periodic digital signal that is used to trigger a DAQ device to perform actions at evenly distributed points in time




30

Clocks & Triggers

Sample Clock

Sample Clocks are clocks that are used to determine when a signal is sampled (or generated)




31

Clocks & Triggers

Clocks are generated by **dividing down** from an onboard timebase, usually an electronic oscillator.

An **electronic oscillator** is a circuit that produces a periodic, oscillating electronic signal



1 MHz quartz crystal electronic oscillator

NI DAQ devices usually have either a 20 MHz, 80 MHz, or 100 MHz oscillator onboard as the master timebase




32

Clocks & Triggers

Triggers

- can be used to cause other actions, such as starting, stopping, or pausing acquisition
- can be generated by analog, digital, or software events



33

NI-DAQmx



ni.com

34

What is NI-DAQmx?

- NI-DAQmx is free driver software.
- It can be used in conjunction with several different programming languages to control thousands of different NI data acquisition devices with a consistent API (Application Programming Interface).

[Download the Latest Version of NI-DAQmx](#)



35

Devices Supported by NI-DAQmx

- Academic devices:
 - NI myDAQ
 - NI ELVIS II
 - NI ELVIS II+
- CompactDAQ
- CompactRIO 904x, 905x
- X Series DAQ
- Digital I/O
- C Series, Network DAQ, and USB DAQ
- . . .

and many more (complete list can be found in the NI-DAQmx Readme)



36

What if I'm Using NI myRIO or NI ELVIS III?

- NI myRIO and NI ELVIS III are not supported by NI-DAQmx.
- Students can create NI-DAQmx simulated devices that behave similarly to real devices.
- Simulated devices can be used to develop and run an application without the data acquisition hardware present in the machine.

Tutorial: [How to create an NI-DAQmx simulated device?](#)



37


Three Ways to Connect with a DAQ Device

NI MAX




NI MAX lets you quickly test the connection to your DAQ device and configure the hardware.

DAQ Assistant Express VI



DAQ Assistant Express VI is a graphical interface for interactively creating, editing, and running NI-DAQmx virtual channels and tasks.

DAQmx API



The LabVIEW DAQmx VIs let you control your hardware with finer options than the DAQ Assistant Express VI.




38

NI Measurement and Automation Explorer (MAX)

Measurement and Automation Explorer (MAX) is an application that installs automatically with the NI-DAQmx driver (and other NI software). MAX informs other programs which devices you have in your system and how they are configured.

You can use MAX to create NI-DAQmx Simulated Devices and build applications without hardware installed.


[Learn More](#)



39

DAQ Assistant Express VI

- The DAQ Assistant is a configuration-based interface for controlling your DAQ instruments
- You can configure things like:
 - Channels
 - Voltage ranges
 - Sampling rate
 - ...and many other aspects of your measurement



41

NI-DAQmx API


ni.com

44

DAQmx API

DAQmx includes an Application Programming Interface (API), which is a library of VIs, functions, classes, attributes, and properties for creating applications for your DAQ device.

DAQmx LabVIEW API



45

DAQmx Core Concepts

Physical Channel

Terminal or pin at which you can measure or generate an analog or digital signal.

Virtual Channel

Contains the physical channel and other channel-specific information.

Task

A collection of one or more virtual channels with timing, triggering, and other properties.

Functions

Performs a specific function in DAQmx.


Properties

Control or set specific properties of your DAQmx session.




47

Physical Channel vs Virtual Channel




48

DAQmx Task





49

DAQmx Programming Model




50

Primary DAQmx VI Palette



51


DAQmx Application



52


Essential DAQmx Functions

Task and Channel Creation using the API occurs in one of two ways:



Browse will allow you to create a new one using DAQ Assistant, select multiple channels, or to navigate more easily

Select a global task or channel from a task or channel control dropdown




Create a local task or channel with a DAQmx VI




53

Essential DAQmx Functions


Configuration using the API occurs in one of three ways:



Input terminals on DAQmx VIs



Polymorphic VI Selectors



DAQmx Property Nodes



54

Essential DAQmx Functions

Acquisition and Generation using the API occurs in one way:




DAQmx Read and Write VIs



55


Essential DAQmx Functions

Cleanup using the API occurs by using the Clear Task VI:



56

10 Functions to Handle 80% of your Data Acquisition Applications



57






Create Virtual Channel

NI-DAQmx Create Virtual Channel

Create

DAQmx Create Virtual Channel

- Creates a local virtual channel and places it into a task
- I/O Type and Measurement Type selected Polymorphically
- Channel Properties selected with input terminals to the VI (or property nodes)
- A task can be wired from Create Virtual Channel to Create Virtual Channel to add multiple channels to a single task




58

Create Virtual Channel

NI-DAQmx Create Virtual Channel

Create

NI-DAQmx Create Virtual Channel VI is used to create a thermocouple virtual channel.



59

Timing

NI-DAQmx Timing



Configure



DAQmx Timing

- Configures the sample clock timing settings for a task
- “Acquisition Mode” from DAQ Assistant is a compilation of Sample Mode and Sample Timing Type properties that must be individually adjusted in the API
- Timing Settings selected with input terminals to the VI (or property nodes)
- Timing Type selected Polymorphically (no Timing VI = On Demand)

DAQmx Timing
SampQuant.SampMode




60

Timing

NI-DAQmx Timing

[Configure](#)

The following LabVIEW block diagram demonstrates the use of the Sample Clock instance of the NI-DAQmx Timing VI to configure a continuous analog output generation with an external sample clock.



61


Trigger

NI-DAQmx Trigger


[Configure](#)

DAQmx Triggering


- Configures the triggering settings for a task
- Trigger Type selected Polymorphically (tasks default to implicit trigger at Start)
- Trigger settings selected with input terminals to the VI (or property nodes)




Start Digital Edge



Start Analog Edge



Reference Digital Pattern




62

Trigger

NI-DAQmx Trigger

[Configure](#)

In the following LabVIEW block diagram, both a start trigger and a reference trigger are configured, using the NI-DAQmx Trigger VI, to occur on digital edges for an analog input operation.




63

Start Task

NI-DAQmx Start Task

[Acquire or Generate](#)

Starts your task. The task is now in the running state.




64


Start Task

NI-DAQmx Start Task

The following LabVIEW block diagram demonstrates a situation where the NI-DAQmx Start function does not need to be used because the analog output generation only consists of a single, software-timed sample.



Conversely, the following LabVIEW block diagram demonstrates a situation where the NI-DAQmx Start function should be used because the NI-DAQmx Read function is executed multiple times to read from the counter.





65

Read

NI-DAQmx Read

Reads samples from the acquisition task.



The Read function adapts to different data types and channel counts




66

Read

NI-DAQmx Read

Acquire or
Generate

In the following LabVIEW block diagram, the NI-DAQmx Read VI has been configured to read multiple samples from multiple analog input virtual channels and return the data as waveforms. Furthermore, since the number of samples per channel input has been wired to a constant value of 10, each time the VI executes it will read 10 samples from each virtual channel.





67

Write

NI-DAQmx Write

Acquire or
Generate

Writes samples to the generation task.



The Read function adapts to different data types and channel counts




68

Write

NI-DAQmx Write

Acquire or
Generate

The following LabVIEW block diagram, for a finite analog output generation, includes a "False" Boolean constant wired to the auto start input of the NI-DAQmx Write VI because the generation is hardware-timed. The NI-DAQmx Write VI has been configured to write multiple samples of analog output data for one channel to the task as an analog waveform.





69

Clear Task

NI-DAQmx Clear Task

Cleanup

Clears the task, and releases all of the resources. If the task needs to be reused, use **Stop Task** instead.



After the DAQmx read, clear the task.




70

Clear Task

NI-DAQmx Clear Task

Cleanup

In the following LabVIEW block diagram, a continuous pulse train is being generated with a counter. The pulse train continues to be output until the While Loop is exited and the NI-DAQmx Clear Task VI executes.



71

Properties

NI-DAQmx Properties

Access all of the properties associated with DAQmx. Properties can be written to or read.



DAQmx Timing

Query the actual sample rate



DAQmx Channel

Specify which terminal pules




72

Properties

NI-DAQmx Properties


In the following LabVIEW block diagram, an NI-DAQmx Channel Property Node is used to enable the hardware lowpass filter and then set the filter cutoff frequency for use with a strain gage measurement.




73

Other DAQmx Considerations


Selecting More than One Channel on a Device



Use colon between channel numbers



Use comma between channel numbers




74


Other DAQmx Considerations

Selecting More than One Channel on a Device


- Channels are zero-indexed
 - Example: This is:
 - 1st Channel
 - of Analog Input
 - on Device 1




- Range (continuous) indicated by ":" 7th, 8th, 9th



- List (discontinuous) indicated by "," 2nd, 4th, 6th



- Mix Range & Lists is allowed 10th, 11th, 12th, 14th, 15th, 16th







75

Other DAQmx Considerations

Waveforms

Waveforms are a data type consisting of cluster of three values used to represent evenly-distributed samples

-  **t0** specifies the start time of the waveform.
-  **dt** specifies the time interval in seconds between data points in the waveform.
-  **Y** specifies the data values of the waveform.



76

Set Up Data Logging in the DAQmx Task



There are extensive resources for quick research into DAQ issues that customers can access to learn and build DAQmx knowledge:

- 

Reading or Writing a Finite Amount of Data



ni.com

83

Acquisition Modes

On Demand: The device produces a requested sample when prompted by a software acquisition request.

Finite Samples: The DAQ device acquires samples at a specified rate until it reaches the number of total requested samples, and then stops acquiring and sends the data to the computer.

Continuous Samples: The DAQ device acquires samples at a specified rate and sends blocks of samples to the computer when requested, until it receives a command to stop acquiring or encounters an error condition.

Hardware-Timed Single Point (HWTSP): The computer acquires data points one at a time from the DAQ device while the device runs off of a sample clock.

Hardware-Timed




84


Reading or Writing a Finite Amount of Data

Two Approaches to Finite Data Transfer

Single-Point



Buffered



85

Reading or Writing a Finite Amount of Data

Point-By-Point Transfer

Read/write one value at a time

- Measure the current temperature
- Set the target speed for a fan

Use a For Loop with a timing function to use point-by-point transfers for multiple samples

- Ramp the output from one value to another over a fixed period of time
- Acquire a fixed number of samples and perform a calculation




86


Reading or Writing a Finite Amount of Data

Acquiring Data Point-by-Point

One Sample



Multiple Samples




87


Reading or Writing a Finite Amount of Data

Generating Data Point-by-Point

One Sample



Multiple Samples



89


Reading or Writing a Finite Amount of Data

Buffered Transfer

Uses a buffer to temporarily store the samples to read or write

Transfers multiple data points to/from the DAQ device at a time


Enables faster transfer than a loop with a timing function



91

Reading or Writing a Finite Amount of Data


Buffered Analog Input



92

Reading or Writing a Finite Amount of Data


Finite Buffered Acquisition



93

Reading or Writing a Finite Amount of Data

Finite Buffered Generation




95

Reading or Writing a Finite Amount of Data


What is Hardware Timing?

Software-Timed



The software and operating system controls the communication rate.

Hardware-Timed



A digital signal, such as a clock on your device, controls the communication rate.



97

Communicating Data Continuously




ni.com

98

Communicating Data Continuously


Continuous Buffered Acquisition Flowchart



99

Communicating Data Continuously

Continuous Buffered Acquisition




- Perform a hardware-timed, continuous buffered acquisition
- Set the sample mode to **Continuous Samples**



100

Communicating Data Continuously

Continuous Buffered Generation



102

Additional Resources

- Learning Badges
 - [Measurement Fundamentals](#)
 - [NI-DAQmx Programming](#)
 - [Sensors and Signals](#)
- Tutorials
 - [Introduction to Data Acquisition](#)
 - [Getting Started with NI-DAQmx](#)
 - [NI-DAQmx Hardware Installation](#)



104